# BurdaStyle For People Who Sew

# **Cutting and Sewing Instructions**

## 110 Тор

Burda sizes 36, 38, 40, 42, 44 Back length approx. 73 cm (29 ins)

## Materials

Brushed knit fabric, width: 150 cm (59 ins) length: 2.30 m (2 5/8 yds) for all sizes.

Twill tape, width: 1 cm (3/8 in) length: 0.65 – 0.65 – 0.70 – 0.70 – 0.70 m (7/8 yd).

Vilene Bias Tape/stay tape.

Recommended fabrics: Fine knits with a soft brushed surface.

### Preparations

Print the pattern out on letter or A4 sized paper. It is very important to not scale the document. Your pattern will print on multiple pages, which you will then tile together. Arrange the sheets on a large, hard and flat surface matching up the numbers and letters (i.e. 6A to 6A).

Trace the pattern pieces from the pattern sheet. Follow lines and details for style 110. Glue pieces 24 and 24a together as marked.

### Burda style magazine patterns do not have seam allowance included.

Seam and hem allowance to be added: Seams and edges 1.5 cm (5/8 in), no allowances on lower edges of front, back, and sleeves and no allowances on long edges and straight narrow edge of scarf.





## Cutting Out

21 front with back yoke, on a fold 1x
22 back, on a fold 1x
23 sleeve 2x
24 scarf 1x

Vilene Bias Tape/stay tape: Iron to wrong side of back armhole edges and back yoke attachment edges.

### Sizes 36-44



Copyright 2012 by Verlag GmbH & Co. KG Aenne Burda, Hubert Burda-Platz 2, D-77652 Offenburg. All models, pattern pieces and drawings are copyrighted, commercial use is prohibited. The publisher shall not be liable for damages caused by improper handling of the cut material, improper execution of the tips and instructions, or improper use of the models are emerging.

# BurdaStyle For People Who Sew

### Sewing

Note: On stretch fabrics, stitch seams with a special stretch stitch or at a narrow zigzag setting.

Gather scarf piece along angled end (= right attachment edge) and along marked line to 13 - 13 - 13.5 - 13.5 - 14 cm (5 1/4 - 5 1/4 - 5 3/8 - 5 3/8 - 5 1/2 ins). Baste attachment edge of scarf to right back yoke attachment edge, right sides facing.

Stitch cut-on back yokes of front to back piece. Press seam allowances toward back.

Working from outer side, lay twill tape on seam allowance of neck edge so that edge of tape meets marked seam line. Begin at one shoulder seam and turn under end of tape which lies on top. Edgestitch tape in place. Trim seam allowance underneath the tape. Turn tape and seam allowance to inside and press edge. Sew inside edge of tape in place by hand.

Stitch side seams and sleeve seams. Trim lower ends of seam allowances at an angle. Neaten edges of seam allowances together and press toward back.

Set in sleeves.

Lay scarf on garment, with wrong side facing right side. Pin lines of gathering over left back yoke attachment seam and stitch between lines of gathering.

# BurdaStyle For People Who Sew

## Additional Information:

**Burda patterns do not include seam and hem allowances.** We recommend adding 1-2 cm (3/8 - 3/4 inch) for seams and 2-5 cm (3/4 - 2 inch/es) for hems. Refer to your specific pattern instructions for exact measurements.

The fabric requirements are based on the fabric used for the original designs. These amounts will change if you use fabric of a different width. The pattern of the fabric determines whether all the pieces must be cut in the same direction or whether some can be reversed to save fabric.

The cutting layout printed with the instructions shows the best way to place the pattern pieces on our original fabric. Fold the fabric double with the right side facing in. The fabric then has a fold edge and a selvedge edge. When cutting from a single fabric layer, the right side should face up.

Pattern pieces which are shown in the cutting layout with broken outlines should be pinned to the fabric with their printed side facing down.

Grey shaded areas in the cutting layout indicate which pieces are to be interfaced.

Transfer the pattern piece lines to the wrong side of your fabric with dressmaker's carbon paper. Hand-baste along lines (e.g. for pockets or centre front) to make them visible on the right side of the fabric.

Have fun sewing, and make sure to upload pictures of your finished sewing project to BurdaStyle.com/projects and link it to the pattern you made it from!

If you have any questions about the pattern or specific instructions please email answers@burdastyle.com and your inquiry will be forwarded to one of our sewing pattern experts.

**The** Fabrics may shrink when laundered for the first time, especially those made of cotton, linen, and rayon. To avoid shrinkage of the finished garment, these fabrics should be pre-treated (washed and dried before cutting out the fabric pieces). Use the temperature settings you plan to use for the finished garment. If you want to test the amount of shrinkage of your fabric, cut a square of the fabric and measure it exactly. Finish the edges, then wash it, and compare the size after washing with the original size.

#### **Symbols** Armhole markings These small lines at the edges of the sleeve and front armhole pieces must meet when the sleeve is set in. Fold **Broken line** In the cutting layout, the broken line indicates the fold edge of a double layer of fabric. Selvedges Button Buttonhole Evelet opening $\times$ Fold line In the pattern overview box, this broken line means that the pattern edge must be placed on a fold and not cut. Joining line Large pattern pieces that cannot fit on the pattern insert sheet will 3 be in two pieces. These pieces must be taped together after they have been traced onto pattern 3a paper. A double line indicates the joining line and small triangles indicate match points. Lengthening If a pattern piece is too long to fit on the pattern insert sheet, you will need to lengthen it when you trace the pattern piece onto pattern paper. Lengthen the pattern from the point of the arrow by the amount indicated 2 20 in centimeters at the arrow. Pleat symbol Fold the pleat in the direction of the arrow. Presser foot A presser foot image indicates seam and topstitching lines. Scissors Scissors indicate slash lines, such as welt pocket openings. (On downloadable patterns, scissors indicate edges to be cut without an added seam allowance.) Seam marks Shown on long seams, these small lines perpendicular to the cutting line indicate edges to be matched. Match the seam marks to one another. Seam numbers Adjacent pattern pieces that must be sewn together are indicated with the same seam numbers. Match pieces with the same numbers. Slit/Placket mark This small, thick line that Placket/slit mark intersects the cutting line indicates beginning or end of a slit or placket. The following symbols will only be found on

The following symbols will only be found on the pattern pieces in the pattern overview box. On the pattern insert sheet and on the downloadable pattern pieces, the words are written out.

Gather	1
	_
Stretch •••••••••	•

# BurdaStyle For People Who Sew



For the best fit, it's important to take precise measurements. Measure your body while wearing underwear or close-fitting garments, and have someone assist you if needed. Use a flexible measuring tape to measure around your body, ensuring the tape is taut but not tight and parallel to the floor. Stand upright with a relaxed posture, and breathe normally while you measure.

**1** Bust: Measure around the fullest part of your bust. Neck circumference: Measure the circumference at the base of the neck and above the collarbone. 2 Waist: Measure around your natural waist, the narrowest part. Hips: Measure horizontally around the fullest part of your bottom and upper thighs.

Additional measurements: 3 Front waist length: Measure from the side base of the neck over the apex of the bust to the natural waistline. Bust depth: Measure from the side base of the neck to the apex of the bust.

Important: Compare your body measurements to the appropriate Burda size chart here or on BurdaStyle. com. Circle each of your body measurements on the size chart since you may want to adjust your pattern to fit a range of sizes. Your Burda size will be different

from your regular store-bought clothing size.

**4** Back waist length: Measure from the base of your neck to the natural waistline. Back width: Measure horizontally between your arm attachment points.

5 Shoulder: Measure from the base of your neck to the tip of your shoulder. Upper arm: Measure around the fullest part of your upper arm.

6 Arm length: With your arm slightly bent, measure from the tip of your shoulder over the elbow to the natural waistline.

### INFANTS' AND TODDLERS' SIZE CHART (based on height) inches

BURDA SIZE US size	56 newborn	62 3mo	68 6mo	74 12mo	80 18mo	86 2T	92 3T	98 4T	104 5	110 6	116 6x
CHEST	17¾	18½	19¼	20	21	21¾	221/2	23	231⁄4	231⁄2	235/8
WAIST	161/2	17¾	181/8	181/8	9¾	20	201/2	21	211⁄4	21¾	22
HIP	181/8	18¾	19¾	201/2	211⁄4	22	23	231⁄4	24	24¾	251⁄4
BACK LENGTH	61/2	6¾	7	71/2	8	85/8	9	91/2	91/8	10½	101/8
ARM LENGTH	61/2	71⁄2	81⁄4	9	101/2	11¼	121⁄4	131/8	141/8	151/8	161/8
NECK	85/8	9	91/2	91/8	91/8	10	101/8	101/8	11	11	11¾

									— L	NECK			078	9	912
WOMEN'S SIZE (	CHAR	۲ (Reg	ular) i	inches											
BURDA SIZE	32	34	36	38	40	42	44	46	48	50	52	54	56	58	60
HEIGHT	66¼	66¼	66¼	66¼	66¼	66¼	661/4	66¼	66¼	661/4	66¼	66¼	661/4	66¼	66¼
BUST	30	311/2	33	34¾	36¼	37¾	391/2	41	431/2	451/2	48	501/2	52¾	551/4	571/2
WAIST	23	241/2	26	273/4	291/4	30¾	321/2	34	36¼	38¾	41	431/2	451/2	48	501/2
HIP	321/2	34	351/2	37	38¾	40¼	41¾	431/2	451/2	48	501/2	<b>52</b> <sup>3</sup> / <sub>4</sub>	551/4	571/2	60
BACK LENGTH	15¾	16	16¼	161/2	165/8	16¾	17	17½	171/4	171/2	173/4	18	18¼	181/2	181/2
SLEEVE LENGTH	231/4	231/4	231/4	23¾	23¾	24	24	24	24	241/2	241/2	243/4	243/4	243/4	243/4
NECK WIDTH	13	13¾	13¾	141/8	141/2	15	153/8	15¾	161/8	161/2	17	171/4	173/4	181/8	181/2
SIDE LEG															
LENGTH	39¾	401/4	40¼	40¾	41	41	411/2	411/2	411/2	41¾	41¾	413/4	421/4	421/2	421/2
FRONT WAIST															
LENGTH	16½	17	171⁄4	17¾	181/8	18½	19	19¼	19¾	201/4	201/2	21	211/4	21¾	221/4
BUST POINT	91/2	91/8	10¼	10¾	111/8	11½	111/8	121/4	123/4	13	131/2	14¼	141/2	14¾	15
UPPER ARM															
CIRCUMFERENCE	91/8	10¼	10¾	111/8	111/2	111/8	121/4	12¾	131/2	141/2	15	15¾	161/2	171/4	18¼

MEN'S SIZE CHART (Regular) inches									
BURDA SIZ	<b>E</b> 44	46	48	50	52	54	56		
HEIGHT	66¼	67¼	68½	69¾	71	71¾	72½		
CHEST	34%	361⁄4	37¾	39¼	41	421⁄2	44		
WAIST	30¾	321⁄4	34	35½	37	38½	41		
SEAT	35½	37	38½	40	40¾	431⁄2	451⁄4		
BACK LENGTH	16½	17	17¼	17½	17¾	18	18¼		
ARM LENGTH	24	24½	24¾	25¼	25½	26	26½		
NECK	14½	15	15¼	15¾	16	16½	17		

### WOMEN'S SIZE CHART (Petite) inches

\* These sizes are Burda petite sizes and differ in height from the regular sizes. The height measurements are from 63 to 66¼ inches. If you are taller than 66¼ inches, you can make alterations to the length of the garment, the sleeve length, etc. to fit your measurements.

BURDA SIZE	16	17	18	19	20	21	22	23
HEIGHT	63	63	63	63	63	63	63	63
BUST	30	31½	33	34¾	36¼	37¾	391/2	41
WAIST	23	241/2	26	27¾	291/4	30¾	321/2	34
HIP	321/2	34	351/2	37	38¾	401⁄4	41¾	431/2
BACK LENGTH	15	15¼	15¾	15¾	16	161/8	16¼	163/8
SLEEVE LENGTH	221/2	221/2	221/2	23	23	231⁄4	231/4	231⁄4
NECK WIDTH	13	13¾	13¾	141/8	14½	15	153/8	15¾
SIDE LEG LENGTH	38¼	38¾	38¾	39	391/2	391/2	39¾	39¾
FRONT WAIST								
LENGTH	15¾	161⁄4	16½	17	171⁄4	17¾	181/8	18½
BUST POINT	91/8	91/2	91/8	10¼	10¾	111/8	11½	111/8
UPPER ARM								
CIRCUMFERENCE	91/8	101⁄4	10¾	111/8	11½	111/8	121⁄4	12¾

### WOMEN'S SIZE CHART (Tall) inches

\* These sizes are Burda tall sizes and differ in height from the regular sizes. The height measurement is 69¼ inches and up. If you are shorter than 69¼ inches, you can make alterations to the length of the garment, the sleeve length, etc. to fit your measurements.

BURDA SIZE	64	68	72	76	80	84	88	92
HEIGHT	691/4	691⁄4	691⁄4	691/4	691⁄4	691/4	691⁄4	691/4
BUST	30	311/2	33	34¾	361⁄4	37¾	391/2	41
WAIST	23	241/2	26	27¾	291⁄4	30¾	321/2	34
HIP	321/2	34	351/2	37	38¾	401/4	413⁄4	431/2
BACK LENGTH	16½	16¾	17	171/8	171⁄4	17½	17¾	18
SLEEVE LENGTH	24	24	24	241⁄2	241/2	24¾	24¾	24¾
NECK WIDTH	13	13¾	13¾	141/8	14½	15	153/8	15¾
SIDE LEG LENGTH	411/2	41¾	41¾	421/4	421/2	421/2	43	43
FRONT WAIST								
LENGTH	171⁄4	17¾	181/8	18½	19	191⁄4	19¾	201⁄4
BUST POINT	91/8	101⁄4	10¾	111/8	11½	111/8	121⁄4	12¾
UPPER ARM								
CIRCUMFERENCE	97/8	101⁄4	10¾	111/8	111/2	111/8	121/4	12¾



# burda Download-Schnitt

# Modell 110 Burda Style 01/2015



Copyright 2015 by Verlag Aenne Burda GmbH & Co. KG, Hubert-Burda Platz 2, D–77652 Offenburg Sämtliche Modelle, Schnittteile und Zeichnungen stehen unter Urheberschutz, gewerbliches Nacharbeiten ist untersagt. Der Verlag haftet nicht für Schäden, die durch unsachgemäße Handhabung des Schnitts, der Materialien, unsachgemäße Ausführung der Tipps und Anleitungen oder unsachgemäße Nutzung der Modelle entstehen.



2a









1d <











2d



















	V 8d				
				Mod. 111 Schlitz / slit шлица, РАЗРЕЗ	
> 7c					
				7d <	

6d ∧

the state of the s

>7d

6e

8e


































14b





16e > 15d 14e

17a<

Kontrollquadrat / test square

Seitenlänge / side length 10 cm (4 inches) **>17**a

17b<















